Methods for Determining Dry Matter of Forages and Grains.

Herb Bucholtz
Department of Animal Science, Dairy Cattle Nutrition
Michigan State University
E. Lansing, MI 48824
August 2007

Microwave Method

Equipment Needed

- 1. Microwave Oven with turntable
- 2. Microwave-Safe Plate: 7-9" diameter. Caution Do not use paper plate, they may burn.
- 3. Gram Scale: Capacity of at least 500 grams, accuracy at least 1.0 gram. Gram scales can be purchased from agricultural supply companies, drug and hardware stores.
- 4. Cup of Water: Be sure container is microwave-safe. This will help prevent the sample from burning when the sample is nearly dry.

Procedure

- 1. Weigh the empty plate & record weight
- 2. Place about 100 grams of chopped forage or cracked/ground grain on plate And record plate + sample weight
- 3. Place in microwave for approximately 4 minutes. Set microwave on high setting.
- 4. After 4 minutes record plate + sample weight
- 5. Place back in microwave for another 2 minutes
- 6. Again record plate + sample weight
- 7. Repeat step # 5 until
 - Plate + sample weight remains unchanged (+/- 1 gram) Sample is now completely dried.
- 8. Subtract the plate weight from the plate+sample weight.

Example of Arithmetic Calculations

- 1. Empty Plate weighted = 200 grams
- 2. Forage or grain sample + plate weighs = 300 grams Sample weighted 100 grams [300 grams (plate + sample) - 200 gram (empty plate)]
- 3. Completely dried plate + sample weighs = 250 grams
- 4. % Dry Matter =

[250 grams (completely dried sample) - 200 grams (empty plate)] = 50 grams

 $50 \text{ grams} \div 100 \text{ grams} = 0.5 \ X \ 100 = 50\% \text{ Dry Matter}$

Koster Moisture Tester TM

Koster Crop Tester Inc. 3077 Nationwide Parkway Brunswick, OH 44212-22361 330-220-2116 Fax: 330-220-1636

kostercrop@aol.com

web: www.kostercroptester.net